# Setting up a RICOH SP111 Printer

Brave search: ricoh sp111 driver ubuntu

https://askubuntu.com/questions/641405/ricoh-sp111-printer-setup-help

https://blog.droidzone.in/2015/09/23/install-ricoh-sp111-laser-printer-in-ubuntu/

Brave search: ricoh sp111 driver ubuntu github

https://superuser.com/questions/1563140/printer-printing-only-one-blank-page-ricoh-sp-111

Go to the \$HOME directory.

```
cd ~/
```

Install necessary dependencies.

```
sudo apt install jbigkit-bin inotify-tools
```

```
sudo apt install --assume-yes imagemagick*
```

Make sure you are in the \$HOME directory.

```
cd ~/
```

Create a folder 'ricoh'.

```
mkdir ricoh
```

Enter the directory you've created.

```
cd ricoh/
```

Clone a GIT repository that contains the driver files.

```
git clone https://github.com/droidzone/ricoh-sp100.git
```

Enter the folder containing the printer driver files.

```
cd ricoh-sp100/
```

Take a look at what the folder contains.

ls

Copy the GDI-printer file pstoricohddst-gdi to /usr/lib/cups/filter/.

```
sudo cp pstoricohddst-gdi /usr/lib/cups/filter/
```

Change the file pstoricohddst-gdi 's ownership to 'root'.

```
sudo chown root:root /usr/lib/cups/filter/pstoricohddst-gdi
```

You can also see the location of this file in the root (system) directory from your file manager.

```
/usr/lib/cups/filter/pstoricohddst-gdi
```

Open a web browser in **private/incognito** browsing mode and type http://localhost:631/ in the *address bar*.

```
http://localhost:631/
```

Follow the steps. The steps are self-explanatory.


OpenPrinting CUPS 2.4.1

## 1. Administration Tab

Connect the Printer to the USB port and power it on.


#### **Printers**

## 2. Add Printer




3. Local Printers: RICOH SP 111 DDST (RICOH SP 111 DDST)

Continue




- 4. **Location:** *Give your printer a name* so that people can find it on the network if you ever share your printer over a network.
- 5. Check the **Share** option if you plan on sharing the printer over a network in the future.


Continue




6. Or Provide a PPD File: Choose file




From the file manager, select the file ~/ricoh/ricoh-sp100/RICOH\_Aficio\_SP\_111.ppd




# 7. Add Printer




Set your printer's default options.







At this stage, the printer should show up in **Settings** -> **Printers**.



Print something to test your printer.

